

# Contamination analysis with InterSpec

<https://sandialabs.github.io/InterSpec/>  
[InterSpec@sandia.gov](mailto:InterSpec@sandia.gov)


Will Johnson

IAEA webinar - 20211117


Download, tutorials, code: <https://sandialabs.github.io/InterSpec>

Feature requests, bugs, support: email [InterSpec@sandia.gov](mailto:InterSpec@sandia.gov)


InterSpec supports determining contamination via adding trace sources to a shielding




Spherical



End-on Cylinder



Side-on Cylinder



Rectangular


# Homogenous and exponentially distributed trace sources




Trace sources can either be

- a) uniform: determined as activity per  $\text{cm}^3$ , total activity, or activity per gram
- b) Exponentially distributed sources, starting from surface facing the detector

Trace sources are volumetric source-terms in the shielding's – they do not affect the attenuation of the shielding



Uniform trace  
source distribution



Exponential

$$f(z) = \frac{S_0}{L} e^{-z/L}$$

$S_0 = \text{total activity } \left(\frac{\text{Bq}}{\text{m}^2}\right)$

$L = \text{relaxation length (cm)}$

63% of activity is within one  
relaxation length of the surface

# Basic idea for analyzing soil measurements in InterSpec



In the “Activity/Shielding Fit” tool, use a shielding composed of soil that is effectively “infinitely large” with one or more trace sources

- The dimension along detector axis should be many attenuation lengths of highest energy peak used for analysis

For 2614 keV, 2 meters in soil would attenuate 99.999% of gammas

- The radial (cylindrical) or width/height (rectangular) dimensions should be large enough to cover the detector’s field of view

For detector 1-meter from ground, needed radius ranges from 15 m (homogeneous), to 210 m (pure surface)

- Increasing dimensions beyond the effectively infinitely large dimensions wont change answers

i.e., for soil contamination, using cylinder with height 2 m, and radius 225 m is a good default to use

Also, when an exponential distribution is selected, dimensions to use will be suggested


You will then fit for trace-source activitie(s)

# Shielding geometries and distances in InterSpec



The “Distance” entered in the “Activity/Shielding Fit” tool is from the center of the shielding to the detector

Example: if you want to represent soil as 2 meter thick, end-on cylinder, with detector 1 meter from the ground:




# Case-study: NORM (Ac-228) concentration in soil



Step 1: Fit the dominant Ac-228 peaks in the spectrum



- Make sure you associate the peaks with Ac-228 by either showing Ac-228 reference lines before fitting the peaks, or manually typing in the association



# Case-study: NORM (Ac-228) concentration in soil (cont)



Step 2: go to the “Activity/Shielding Fit” tool






## Case-study: NORM (Ac-228) concentration in soil (cont)



Step 3: select “Cylindrical: end-on” geometry, or “Rectangular”





## Case-study: NORM (Ac-228) concentration in soil (cont)



Step 4: Add a “Material” shielding, and choose “Soil” or other material

Detector: AEGIS

Distance: 10 m

Geometry: Cylindrical: end-on

Add Shielding: **Material** Generic



Detector: AEGIS

Distance: 10 m

Geometry: Cylindrical: end-on

Add Shielding: Material Generic

Soil

$\rho=1.6 \text{ g/cm}^3$ ,  $\overline{AN}\sim 10.4$



Radius 1.0 cm ☐ Fit

Half-Length 1.0 cm ☐ Fit

# Case-study: NORM (Ac-228) concentration in soil (cont)



Step 5: Add a trace source by clicking on the “+” button



## Case-study: NORM (Ac-228) concentration in soil (cont)



Step 6: Select "Ac228" as the trace source, select to fit activity, and choose activity type

Detector: AEGIS

Distance: 10 m

Geometry: Cylindrical: end-on

Add Shielding: ☒ Material ☐ Generic

☒ Soil  $\rho=1.6 \text{ g/cm}^3, \overline{AN}\sim 10.4$

Radius: 1.0 cm ☐ Fit

Half-Length: 1.0 cm ☐ Fit

Trace Source

Nuclide: ☒ Select

Activity: **Ac228**

☐ Fit activity value

Detector: AEGIS

Distance: 10 m

Geometry: Cylindrical: end-on

Add Shielding: ☒ Material ☐ Generic

☒ Soil  $\rho=1.6 \text{ g/cm}^3, \overline{AN}\sim 10.4$

Radius: 1.0 cm ☐ Fit

Half-Length: 1.0 cm ☐ Fit

Trace Source

Nuclide: Ac228

Activity: 85.3110 MBq

☒ Fit activity value

Total  
per cm<sup>3</sup>  
per m<sup>2</sup> exp  
**per gram**

## Case-study: NORM (Ac-228) concentration in soil (cont)



Step 8: Enter in dimensions you want.

Ex., 50 m radius, and 2 m half-length (4 m total depth)

**Detector: AEGIS**

Distance: 2 m

Geometry: Cylindrical: end-on

Add Shielding: ☒ Material ☐ Generic

☒ Soil  $\rho=1.6 \text{ g/cm}^3, \overline{AN}\sim 10.4$

Radius 225.00 m ☐ Fit

Half-Length 1.00 m ☐ Fit

Trace Source

Nuclide Ac228

Activity 22.9574 mBq per gram

☒ Fit activity value

Detector was 1 meter from ground, but since using 1 meter cylinder half-length, distance is 2 meter to center of soil shielding

Make sure you aren't fitting for dimensions – this doesn't make sense in this context


# Case-study: NORM (Ac-228) concentration in soil (cont)



Step 9: Make sure you are using correct detector response function, and other options selected as you want, and hit "Perform Model Fit"

Further calculation details available in log

Make sure your peaks are all within reasonable numbers of sigma of each other





Activity will be updated 23 mBq/gram

# Case-study: Eu152 surface contamination (cont)



There are a couple ways you could represent this scenario

1. As an exponential surface contamination, with very short relaxation length
2. As a thin “air” volume, with uniform trace-source distribution





## Case-study: Eu152 surface contamination (cont)



The steps for analysis is same as last example, but this time choose a rectangular geometry

“Width” and “Height” are entered as half-values – this makes things easier when there are multiple layers

Choose a total thickness of 1 cm, for convenience

Detector: AEGIS

Distance: 100.5 cm

Geometry: Rectangular

Add Shielding: Material Generic

Air

$\rho=0.0013 \text{ g/cm}^3, \overline{AN}\sim 7.4$

Half-Width 10.50 m ☐ Fit

Half-Height 10.50 m ☐ Fit

Half-Depth 5.00 mm ☐ Fit

Trace Source

Nuclide Eu152

Activity 246.4390 mBq per cm<sup>3</sup>

☒ Fit activity value

Add 0.5 cm to distance to make up for 1 cm thickness

Multiplying by 1 cm, gives surface contamination of 246 mBq/cm<sup>2</sup> (known value: 252 mBq/cm<sup>2</sup>)



# Case study: Chernobyl measurements

Do same steps as previous examples, but:

- fit peaks for Eu154, Cs137, Co60, and Cs134
- Use a end-on cylindrical, or rectangular geometry, with sufficiently large dimensions
- Add a trace source for each of the four nuclides
- Select “**per m<sup>2</sup> exp**” activity type – this will cause a “Relaxation Distance” enter form to appear
- Enter “3 cm” for relaxation distance

Chernobyl - Point 1

Nuclide	Activity
Eu154	6.24 ± 0.15 kBq/m <sup>2</sup>
Cs137	1.43 ± 0.01 MBq/m <sup>2</sup>
Co60	206.9 ± 14.2 Bq/m <sup>2</sup>
Cs134	368.78 ± 38.7 kBq/m <sup>2</sup>

The screenshot shows the 'Detector: ChernobylHpgeEfficiency' window. Key settings include:
 

- Distance: 3 m
- Geometry: Cylindrical: end-on
- Add Shielding: Material (selected), Generic
- Soil (selected in the shield dropdown)
- ρ=1.6 g/cm<sup>3</sup>, AN~10.4
- Radius: 200.00 m (Fit checkbox)
- Half-Length: 2.00 m (Fit checkbox)
- Trace Source section:
  - Nuclide: Eu154
  - Activity: 6.1408 kBq
  - Fit activity: ☒
  - Relaxation Distance: 3.0 cm

 A red circle highlights the activity type dropdown menu, which is open and shows 'Total per cm<sup>3</sup>', '✓ per m<sup>2</sup> exp' (selected), and 'per gram'. Red arrows point from the list items to these specific settings in the software interface.

# Some warnings about these calculations in InterSpec



- Non-spherical geometries and trace sources are new capabilities added to InterSpec v1.0.9\_rc1 – released today.
  - There are bound to be some improvements and issues that need to be fixed
- The angular response of the detectors is not taken into account.
  - Not typically a large effect (think 10%), but has not been rigorously evaluated
  - This is expected to be added in the future

Download, tutorials, code: <https://sandialabs.github.io/InterSpec>

Feature requests, bugs, support: email [InterSpec@sandia.gov](mailto:InterSpec@sandia.gov)

# Comparison of results



## Eu152 - 21m x 21m surface contamination

	Truth	InterSpec	ISOCS	ISOTOPIC PS	ISOTOPIC %
<b>AEGIS</b>	<b>2520 bq/m<sup>2</sup></b>	2459 ± 18 bq/m <sup>2</sup>	2632 ± 62 bq/m <sup>2</sup>	2601 ± 86 bq/m <sup>2</sup>	2309 ± 44 bq/m <sup>2</sup>
<b>MicroDetective</b>	<b>2520 bq/m<sup>2</sup></b>	2349 ± 41 bq/m <sup>2</sup>	—	2834 ± 93 bq/m <sup>2</sup>	2406 ± 73 bq/m <sup>2</sup>

## Ac228 Homogeneous

	LabSOCS	InterSpec	ISOCS	ISOTOPIC PS	ISOTOPIC %	Manual
<b>AEGIS</b>	—	23.7 ± 0.4 bq/kg	26.15 ± 0.89 bq/kg	23.92 ± 2.25 bq/kg	20.87 ± 0.94 bq/kg	21.14 ± 1.68 bq/kg
<b>MicroDetective</b>	—	20.8 ± 0.8 bq/kg	—	25.70 ± 2.26 bq/kg	25.59 ± 2.23 bq/kg	—
<b>Lab</b>	<b>21.30 ± 0.40 bq/kg</b>	—	—	—	—	—

## Chernobyl - Point 1

Nuclide	InterSpec	ISOTOPIC
<b>Eu154</b>	6.24 ± 0.15 kBq/m <sup>2</sup>	6.61 ± 0.16 kBq/m <sup>2</sup>
<b>Cs137</b>	1.43 ± 0.01 MBq/m <sup>2</sup>	1.47 ± 0.01 MBq/m <sup>2</sup>
<b>Co60</b>	206.9 ± 14.2 Bq/m <sup>2</sup>	245.6 ± 22.6 Bq/m <sup>2</sup>
<b>Cs134</b>	368.78 ± 38.7 kBq/m <sup>2</sup>	349.5 ± 70.6 Bq/m <sup>2</sup>